

RegPerfect 8.1.0.1 is Available Now!

Teledyne Monitor Labs (TML) is excited to announce the release of RegPerfect 8.1.0.1 (RPv8101.0)! This version of RegPerfect will include all the functionality of RPv8002.0 + RPv8100.0 Beta + Q1 2024 Interim Reporting Updates. Some highlights of this new version are:

- Reporting of existing XML data elements will continue to be supported, with the addition of Daily Backstop data required under the Good Neighbor Plan.
- The new MATS 2.0 data and elements will NOT be supported in XML format.
- Forms for configuring and/or entering data into RegPerfect for the MATS 2.0 elements have been added, as well as updated reports to display this entered data are included.
 - For example
 - Emissions – MATS monitor and derived hourly values, daily backstop data
 - QA/Cert – PM correlation tests, PM RCA & RAA, HCl RAA, HCl CGA, Quarterly Compliance Report, etc.
- A JSON file with the new MATS 2.0 data and elements can be generated.
- Additional enhancements and bug fixes throughout the suite of apps and reports are also included in the release

Please contact Tech Support for more information and to find out how to get this latest version.

Tech Support

TMLTechSupport@Teledyne.com

800-846-6062 Option 2